

---

**Aditya-L1**

**SOLAR LOW ENERGY X-RAY  
SPECTROMETER  
(SoLEXS)**

---

**Data Analysis Guide**

**Version 1.0**



**U. R. RAO SATELLITE CENTRE**

**INDIAN SPACE RESEARCH ORGANISATION**

**BENGALURU**

# Change History

Version number	Date	Affected section, Figure, Table	Nature of change	Description
1.0	January 2025	-	-	First Release

\* A: Addition, M: Modification, D: Deletion

# Contents

<b>1</b>	<b>Introduction</b>	<b>1</b>
<b>2</b>	<b>SoLEXS Data Products</b>	<b>2</b>
2.1	Level-1 Data Products . . . . .	2
2.1.1	Good Time Intervals (GTI) File . . . . .	2
2.1.2	Light Curve (LC) File . . . . .	2
2.1.3	Pulse Invariant (PI) Spectral File . . . . .	2
2.2	Time in SoLEXS Data Products . . . . .	3
2.3	L1 Data Naming Convention . . . . .	3
2.4	Calibration Database (CALDB) . . . . .	4
<b>3</b>	<b>SoLEXS_Tools</b>	<b>4</b>
3.1	Requirements . . . . .	4
3.2	Installation . . . . .	4
3.3	Command Line Tools . . . . .	4
3.3.1	<code>solexs-time2utc</code> . . . . .	5
3.3.2	<code>solexs-utc2time</code> . . . . .	5
3.3.3	<code>solexs-genlc</code> . . . . .	5
3.3.4	<code>solexs-genspec</code> . . . . .	6
3.3.5	<code>solexs-genmultispec</code> . . . . .	6
<b>4</b>	<b>Spectral Analysis with SoLEXS Data</b>	<b>7</b>
4.1	Detector Selection for Spectral Analysis . . . . .	7
4.2	Type-I Pulse Invariant (PI) Spectral File . . . . .	7
4.3	Workflow for Spectral Analysis . . . . .	8
4.4	Using XSPEC for Spectral Analysis . . . . .	9
4.4.1	Select a Solar Flare . . . . .	9
4.4.2	Generate Type-I PI Files . . . . .	10
4.4.3	Load the Spectrum in XSPEC . . . . .	11
4.4.4	Choose a Spectral Model . . . . .	11
4.4.5	Fit the Model to the Data . . . . .	12
4.5	Notes on SoLEXS Spectral Analysis . . . . .	14
4.5.1	Channel Binning in SoLEXS . . . . .	14
4.5.2	Response Calibration Below 2.8 keV . . . . .	15
4.5.3	Detector Selection for Spectral Analysis . . . . .	15
4.5.4	Errors on Spectral Data . . . . .	16
4.5.5	Resolution Degradation at High Count Rates . . . . .	16

# 1 Introduction

Aditya-L1 is India's first space-based solar mission developed by the Indian Space Research Organisation (ISRO). Launched on 2 September 2023, the spacecraft was inserted in a halo orbit around Lagrangian point 1 (L1) of the Sun-Earth system on 6 January 2024. Solar Low Energy X-ray Spectrometer (SoLEXS), one of the payloads on Aditya-L1, is a sun-as-a-star spectrometer in the energy range of 2 keV to 22 keV. It employs Silicon Drift Detector (SDD) as sensor element to detect energy. SDD is particularly suited for solar soft X-ray flux monitoring because of its high-event rate handling capability ( $\sim 10^5$  counts/second) and low noise performance with energy FWHM of  $\sim 170$  eV at 5.9 keV. The on-board processing unit histograms the recorded energies of the X-ray events to build a spectrum every second to capture the impulsive solar activity. To cover an extensive dynamic range from A class to X class flares, the payload has two apertures with geometric areas of 7.1 and 0.1 mm<sup>2</sup>. The detailed specifications of the payload are provided in Table 1.

This document serves as a data analysis guide for working with SoLEXS data. It introduces the SoLEXS data products, calibration database, and a python package named SoLEXS\_Tools. It also outlines a workflow for preparing and analyzing SoLEXS data using spectral fitting tools, along with an example case study of a solar flare. By following the instructions in this document, users will be able to derive important plasma parameters such as temperature, emission measure, and elemental abundances from SoLEXS data.

Table 1: Specifications of SoLEXS

Parameter	Specification
Energy Range	2 – 22 keV (2.8 – 22 keV for spectral fitting) <sup>1</sup>
Energy Resolution	$\sim 170$ eV @ 5.9 keV
Time Cadence	Spectral Channel: 1 second Temporal Channel: 1 second
Detector	
Type	Silicon Drift Detector (SDD)
Number	2 (named SDD1 & SDD2)
Active Area	30 mm <sup>2</sup>
Thickness	450 $\pm$ 20 $\mu$ m
Entrance Window	8 $\mu$ m thick Be
Aperture Area	SDD1: 7.106 mm <sup>2</sup> SDD2: 0.106 mm <sup>2</sup>
Field of View	SDD1: $\pm 1.8^\circ$ SDD2: $\pm 1.3^\circ$
Calibration Source	Fe-55 with Ti foil
Digital Pulse Processing parameters	
Pulse peaking time (triangular pulse)	Spectral Channel: 2 $\mu$ s Temporal Channel: 0.35 $\mu$ s
Number of channels in the spectrum	340
Channel Width	1 - 168 channel: $\sim 47.6$ eV 169 - 340 channel: $\sim 95.2$ eV

<sup>1</sup>The instrument response between 2 to 2.8 keV is currently uncertain, and efforts are underway to optimize and verify it. Users are advised to use spectral data above 2.8 keV for modeling. This will be updated in the next release.

---

## 2 SoLEXS Data Products

SoLEXS data is hosted on the PRADAN website<sup>2</sup>, where it is made available in a day-wise format. Users can select and download the required files using various options provided on the website.

### 2.1 Level-1 Data Products

SoLEXS Level-1 (L1) data files are provided in FITS (Flexible Image Transport System) format, compressed using the gzip algorithm. Additionally, all L1 data files conform to the OGIP standards, ensuring compatibility with standard astronomical data analysis tools like XSPEC<sup>3</sup> and Sherpa<sup>4</sup>.

#### 2.1.1 Good Time Intervals (GTI) File

The level-1 GTI file lists the time intervals during which the detector was collecting valid data. These intervals are determined based on several criteria:

1. The Sun was within the field of view of the instrument.
2. The specific detector (SDD1 or SDD2) was operational.
3. The health parameters of the instrument were within the recommended ranges.

#### 2.1.2 Light Curve (LC) File

The level-1 LC file provides a time series of counts detected in the energy range 2–22 keV at a cadence of one second for a given day.

The RATE extension includes the following columns:

1. TIME: Unix Time.
2. COUNTS: Counts per second in the energy range 2–22 keV .

#### 2.1.3 Pulse Invariant (PI) Spectral File

The level-1 PI file is a Type-II Pulse Invariant (PI) spectral file containing energy-resolved calibrated spectra recorded at a cadence of one second for a given day. Each row in the SPECTRUM extension corresponds to a spectrum recorded with a one second integration time. The SPECTRUM extension includes the following columns:

1. TSTART: The start time of the integration interval.
2. TELAPSE: The integration time for the spectrum. For SoLEXS data, this is one second.
3. SPEC\_NUM: A unique identifier for the spectrum within the file.
4. CHANNEL: The energy channel index.
5. COUNTS: The spectral counts detected in each energy channel during the integration interval.
6. EXPOSURE: The effective integration time after applying deadtime correction. (Note: Deadtime correction is not currently applied, so EXPOSURE is equal to TELAPSE.)

---

<sup>2</sup><https://pradan.issdc.gov.in/pradan/all>

<sup>3</sup><https://heasarc.gsfc.nasa.gov/xanadu/xspec/>

<sup>4</sup><https://sherpa.readthedocs.io>

---

## 2.2 Time in SoLEXS Data Products

All time-related data in SoLEXS files is recorded in Unix time, which represents the number of seconds elapsed since January 1, 1970, 00:00:00 UTC. Unix time is widely adopted in computing beyond its original application as the system time for Unix. Unix time is available in almost all system programming APIs. SoLEXS\_Tools also provides utilities to perform such conversions described in section 3.3.1.

## 2.3 L1 Data Naming Convention

The naming convention for a SoLEXS Level-1 (L1) data file downloaded from PRADAN is as follows:

`AL1_SLX_L1_YYYYMMDD_vM.n.zip`

Where:

- **YYYYMMDD**: Represents the year, month, and day of the observation.
- **vM.n**: Represents the version of the data product

After downloading and unzipping the `.zip` file, a directory is created with the same name as the zip file. For example:

`AL1_SLX_L1_YYYYMMDD_vM.n/`

This directory contains subdirectories for each detector **SDD1** and **SDD2**. Each detector-wise directory contains the respective L1 files for that detector. The naming convention of L1 data products will be as follows:

- **GTI File**: `AL1_SOLEXS_YYYYMMDD_SDDn_L1.gti.gz`
- **LC File**: `AL1_SOLEXS_YYYYMMDD_SDDn_L1.lc.gz`
- **PI File**: `AL1_SOLEXS_YYYYMMDD_SDDn_L1.pi.gz`

After unzipping the downloaded zip file, the file will generate following directory structure:

```
AL1_SLX_L1_YYYYMMDD_vM.n/  
  SDD1/  
    AL1_SOLEXS_YYYYMMDD_SDD1_L1.gti.gz  
    AL1_SOLEXS_YYYYMMDD_SDD1_L1.lc.gz  
    AL1_SOLEXS_YYYYMMDD_SDD1_L1.pi.gz  
  SDD2/  
    AL1_SOLEXS_YYYYMMDD_SDD2_L1.gti.gz  
    AL1_SOLEXS_YYYYMMDD_SDD2_L1.lc.gz  
    AL1_SOLEXS_YYYYMMDD_SDD2_L1.pi.gz
```

**Note:** If a particular detector has no valid observations on a given day, the LC and PI files for that detector will not be generated.

---

## 2.4 Calibration Database (CALDB)

The Calibration Database (CALDB) for SoLEXS provides essential files that describe the instrument's response characteristics. These files are crucial for converting raw photon counts into meaningful physical parameters during spectral analysis. The CALDB is organized to include:

- Auxiliary Response File (ARF)
- Redistribution Matrix File (RMF)

The CALDB files are stored within the directory structure of the SoLEXS\_Tools package, and their paths are automatically resolved during the installation.

## 3 SoLEXS\_Tools

SoLEXS\_Tools is a Python package developed to facilitate the processing and preparation of the SoLEXS data. It provides essential tools and utilities generating and managing spectral data and calibration files, enabling users to perform spectral analysis using specialized tools such as XSPEC or Sherpa. The package includes SoLEXS calibration database (CALDB), which provides essential calibration files such as Auxiliary Response File (ARF) and Redistribution Matrix File (RMF).

### 3.1 Requirements

Before installing SoLEXS\_Tools, ensure that the following dependencies are met:

1. Python 3.6 or Higher

Check Python Version

```
python3 --version
```

2. External Python Packages

NumPy, Astropy

Install the dependencies using pip:

```
pip install numpy astropy
```

### 3.2 Installation

Download the SoLEXS\_Tools package from Pradan website and follow the instructions given below:

```
tar xvf solexs_tools-m.n.tar.gz
cd solexs_tools
python setup.py build
python setup.py install
```

### 3.3 Command Line Tools

SoLEXS\_Tools, when installed, creates several command-line tools automatically. These tools simplify common data processing tasks. Once installed, these commands can be directly accessed from the terminal.

---

### 3.3.1 solexs-time2utc

Convert a Unix timestamp to UTC in ISO 8601 format.

Usage:

```
solexs-time2utc <unix_time>
```

Arguments:

- <unix\_time>: Unix timestamp to convert.

Example:

```
solexs-time2utc 1707715800  
# Output: UTC Time: 2024-02-12T11:00:00
```

### 3.3.2 solexs-utc2time

Convert UTC in ISO 8601 format to a Unix timestamp.

Usage:

```
solexs-utc2time <utc_time>
```

Arguments:

- <utc\_time>: UTC time in ISO 8601 format.

Example:

```
solexs-utc2time 2024-02-12T11:00:00  
# Output: Unix Timestamp: 1707715800
```

### 3.3.3 solexs-genlc

Generate a light curve file from Level 1 PI spectrogram file (Type II) for a specified energy range.

Usage:

```
solexs-genlc -i <l1_pi_file> -elo <ene_low> -ehi <ene_high> \  
[-tbin <time_bin>] [-o <outfile>] [--clobber <True/False>]
```

Arguments:

- <l1\_pi\_file>: Path to the Level 1 PI spectrogram file (Type II)
- <ene\_low>: Lower energy limit in keV
- <ene\_high>: Higher energy limit in keV
- <time\_bin>: Time bin size in seconds (Default set to one second)

Example:

```
solexs-genlc -i AL1_SOLEXS_20240212/L1/SDD2/AL1_SOLEXS_20240212_SDD2_L1.pi.gz \  
-elo 2 -ehi 22 -tbin 60
```



---

### 3.3.4 solexs-genspec

Generate a type-I PI spectral file from Level 1 PI spectrogram file (Type II) for a specified time range.

Usage:

```
solexs-genspec -i <l1_pi_file> -tstart <tstart> -tstop <tstop> \  
-gti <l1_gti_file> [-o <outfile>] [--clobber <True/False>]
```

Arguments:

- <l1\_pi\_file>: Path to the Level 1 PI spectrogram file (Type II)
- <tstart>: Start time in Unix seconds
- <tstop>: Stop time in Unix seconds
- <l1\_gti\_file>: Path to the Level 1 Good Time Interval File

Example:

```
solexs-genspec -i AL1_SOLEXS_20240212_SDD2_L1.pi.gz \  
-tstart 1707715800 -tstop 1707715860 \  
-gti AL1_SOLEXS_20240212_SDD2_L1.gti.gz
```

### 3.3.5 solexs-genmultispec

Generate multiple type-I PI spectral files from Level 1 PI spectrogram file (Type II) for a specified time range and time binning.

Usage:

```
solexs-genspec -i <l1_pi_file> -tstart <tstart> -tstop <tstop> -tbin <tme_bin>\  
-gti <l1_gti_file> [-o <outdir>] [--clobber <True/False>]
```

Arguments:

- <l1\_pi\_file>: Path to the Level 1 PI spectrogram file (Type II)
- <tstart>: Start time in Unix seconds
- <tstop>: Stop time in Unix seconds
- <time\_bin>: Time bin size in seconds
- <l1\_gti\_file>: Path to the Level 1 Good Time Interval File

Example:

```
solexs-genspec -i AL1_SOLEXS_20240212_SDD2_L1.pi.gz \  
-tstart 1707715800 -tstop 1707715860 -tbin 10\  
-gti AL1_SOLEXS_20240212_SDD2_L1.gti.gz
```

---

## 4 Spectral Analysis with SoLEXS Data

The most important radiation mechanism producing X-ray emission in SoLEXS's energy range are thermal bremsstrahlung continuum and line emission from highly ionized atoms of various elements in the solar corona. SoLEXS data can be used for diagnosis of physical parameters, such as plasma temperature, emission measure, and elemental abundances. This process requires spectral fitting of the data from Type-I Pulse Invariant (PI) spectral files and the calibration files (ARF and RMF). Tools such as XSPEC, Sherpa, or OSPEX can be used for spectral fitting.

### 4.1 Detector Selection for Spectral Analysis

While downloading the data from the PRADAN website, users can apply the quality filter criteria to check which detector (SDD1 or SDD2) is recommended for spectral analysis. The quality filter values are as follows:

- 1: Neither SDD1 nor SDD2 is suitable for spectral analysis.
- 2: SDD1 is recommended for spectral analysis.
- 3: SDD2 is recommended for spectral analysis.
- 4: Both SDD1 and SDD2 are suitable for spectral analysis.

### 4.2 Type-I Pulse Invariant (PI) Spectral File

The `solexs-genspec` and `solexs-genmultispec` commands in `SoLEXS_Tools` generate Type-I PI spectral file(s) from the input L1 Type-II PI spectral file. The `SPECTRUM` extension of the Type-I PI file contains a single spectrum integrated over the user-specified time range, unlike Type-II PI file, which contains multiple spectra at one second cadence for the entire day. The Type-I PI spectral file is OGIP compliant and includes all the necessary preprocessing to make it ready for spectral analysis.

The header of the `SPECTRUM` extension includes metadata such as the observation time start (`TSTART`), observation time end (`TSTOP`), exposure time (`EXPOSURE`), and calibration file paths (`RESPFILE` for RMF and `ANCRFILE` for ARF). The `SPECTRUM` extension also includes the following columns:

1. `CHANNEL`: Energy channel numbers.
2. `COUNTS`: Counts in each energy channel.
3. `STAT_ERR`: Statistical errors for the counts (assumed Poissonian).
4. `SYS_ERR`: Systematic errors for the counts.
5. `QUALITY`: Quality flag, where 1 indicates bad quality and 0 indicates good quality.

---

## 4.3 Workflow for Spectral Analysis

The following steps outline the typical workflow for performing spectral analysis with SoLEXS data:

### 1. Select a Solar Flare:

- Plot the light curve using L1 LC file using visualization tools such as xronos, fv, or python's matplotlib.
- Identify the phase of the flare for spectral analysis. Ensure that the selected integration time provides a reliable signal-to-noise ratio for the spectrum.
- Note the start and end times of the selected phase.

### 2. Generate Type-I PI File:

- Use the `solexs-genspec/solexs-genmultispec` command to generate Type-I PI file(s) for the selected time range.
- The output will be OGIP-compliant Type-I PI spectral file(s), to be used in spectral fitting tools like XSPEC or Sherpa.

### 3. Load the Data in a Spectral Analysis Tool:

- Import the Type-I PI file into XSPEC or Sherpa.
- Ensure the response files (ARF and RMF) are correctly loaded with correct paths. The names and location of the files are written in the header.
- Ensure appropriate errors on the spectrum are loaded. The statistical (Poissonian) error is available in `STAT_ERR` column.
- The systematic error (`SYS_ERR` column) is currently set to zeros. Add systematic error if necessary. We recommend using systematic error of 4%.

### 4. Choose a Spectral Model:

- SoLEXS spectrum, during solar flares, can be modeled with thermal emission model (continuum and lines) characterized by temperature, emission measure, and abundances of various elements.
- Following thermal emission models are available for spectral fitting.
  - `chspec`<sup>5</sup>: Local model in XSPEC with CHIANTI atomic database
  - `vvapex`<sup>6</sup>: XSPEC model with AtomDB atomic database
  - `vth_abun`<sup>7</sup>: OSPEX model with CHIANTI atomic database

We recommend using `chspec` for SoLEXS spectral modelling.

---

<sup>5</sup><https://github.com/xastprl/chspec>

<sup>6</sup><https://heasarc.gsfc.nasa.gov/xanadu/xspec/manual/node134.html>

<sup>7</sup>[https://hesperia.gsfc.nasa.gov/ssw/packages/xray/idl/f\\_vth\\_abun.pro](https://hesperia.gsfc.nasa.gov/ssw/packages/xray/idl/f_vth_abun.pro)

---

## 5. Fit the Model to the Data:

- Provide the initial guesses and bounds for the model parameters.
- Select the spectral energy range for fitting. The lower limit should not be less than 2.8 keV (Refer section 4.5.2). The upper limit should be determined based on the signal-to-noise ratio.
- Perform fitting to minimize the fit statistic ( $\chi^2$ ).
- Obtain corresponding best-fit model parameters and their error estimates.
- Evaluate the goodness-of-fit using statistical measures (reduced  $\chi^2$ ) and residuals.

## 4.4 Using XSPEC for Spectral Analysis

This example demonstrates the analysis of an M6 solar flare observed by SoLEXS on February 12, 2024, starting at 03:23 UT and peaking at 03:48 UT. The analysis focuses on a 30-second interval near the flare's peak.

### 4.4.1 Select a Solar Flare

- Use the Level-1 LC file to visualize the light curve data for the given day as illustrated in Figure 1.




Figure 1: Light Curve data for February 12, 2024

- Select a flare for spectral analysis. For example, an M6 solar flare, biggest flare of the selected day, is used. Note down the start and stop time of the flare.




Figure 2: Light Curve data for M6 solar flare starting at 03:23 UT, peaking at 03:48 UT, and ending at 04:10 UT

#### 4.4.2 Generate Type-I PI Files

Use the `solexs-genmultispec` command to create Type-I PI files for the selected start time of 03:23:15 UT (1707688395), stop time of 04:10:15 UT (1707691215), and time binning (30 seconds).

```
solexs-genmultispec -i AL1_SOLEXS_20240212/L1/SDD2/AL1_SOLEXS_20240212_SDD2_L1.pi.gz \
-tstart 1707688395 -tstop 1707691215 -tbin 30 \
-gti AL1_SOLEXS_20240212/L1/SDD2/AL1_SOLEXS_20240212_SDD2_L1.gti.gz
```

---

### 4.4.3 Load the Spectrum in XSPEC

For example, an integration of 30-seconds during peak of the selected flare, with start time 03:46:45 UT and stop time 03:47:15 UT (Figure 2) will be used for spectral fitting. Start XSPEC and load the generated PI file.

```
xspec
```

```
XSPEC version: 12.14.1
```

```
Build Date/Time: Thu Sep 5 15:37:06 2024
```

```
XSPEC12>data AL1_SOLEXS_20240212_SDD2_L1_034645_034715.pi
```

```
1 spectrum in use
```

```
Spectral Data File: AL1_SOLEXS_20240212_SDD2_L1_034645_034715.pi Spectrum 1
```

```
Net count rate (cts/s) for Spectrum:1 5.752e+03 +/- 1.385e+01
```

```
Assigned to Data Group 1 and Plot Group 1
```

```
Noticed Channels: 1-340
```

```
Telescope: AL1 Instrument: SoLEXS Channel Type: PI
```

```
Exposure Time: 30 sec
```

```
Using fit statistic: chi
```

```
Using Response (RMF) File /path/to/solexs_gaussian_SDD2_512.rmf
```

```
Using Auxiliary Response (ARF) File /path/to/solexs_arf_SDD2.fits
```

### 4.4.4 Choose a Spectral Model

```
XSPEC12>lmod chspec /path/to/chspec/
```

```
Model package chspec successfully loaded.
```

```
XSPEC12>model chisoth
```

```
Model chisoth<1> Source No.: 1 Active/On
```

Model	Model	Component	Parameter	Unit	Value	
par	comp					
1	1	chisoth	logT	K	7.00000	frozen
2	1	chisoth	He		10.9000	frozen
3	1	chisoth	Li		1.64000	frozen
4	1	chisoth	Be		1.94000	frozen
5	1	chisoth	B		3.09000	frozen
6	1	chisoth	C		8.59000	frozen
7	1	chisoth	N		8.00000	frozen
8	1	chisoth	O		8.89000	frozen
9	1	chisoth	F		4.56000	frozen
10	1	chisoth	Ne		8.08000	frozen
11	1	chisoth	Na		6.93000	frozen
12	1	chisoth	Mg		8.15000	frozen
13	1	chisoth	Al		7.04000	frozen
14	1	chisoth	Si		8.10000	frozen

---

15	1	chisoth	P	5.45000	frozen
16	1	chisoth	S	7.27000	frozen
17	1	chisoth	Cl	5.50000	frozen
18	1	chisoth	Ar	6.58000	frozen
19	1	chisoth	K	5.67000	frozen
20	1	chisoth	Ca	6.93000	frozen
21	1	chisoth	Sc	3.71000	frozen
22	1	chisoth	Ti	5.56000	frozen
23	1	chisoth	V	4.54000	frozen
24	1	chisoth	Cr	6.21000	frozen
25	1	chisoth	Mn	5.93000	frozen
26	1	chisoth	Fe	8.10000	frozen
27	1	chisoth	Co	5.46000	frozen
28	1	chisoth	Ni	6.84000	frozen
29	1	chisoth	Cu	4.75000	frozen
30	1	chisoth	Zn	5.14000	frozen
31	1	chisoth	norm	1.00000	+/- 0.0

---

Rebinning table to response energy bins: NEW NBINS 2250 OLD NBINS 0

Fit statistic : Chi-Squared 57919.79 using 151 bins.

Test statistic : Chi-Squared 57919.79 using 151 bins.

Null hypothesis probability of 0.00e+00 with 149 degrees of freedom

Current data and model not fit yet.

#### 4.4.5 Fit the Model to the Data

- Provide the initial guesses and bounds for the model parameters. Thaw temperature, norm, abundances of Ar, Ca, Fe, and Ni. Keep rest of the model parameters frozen.

```
XSPEC12>thaw 18 20 26 28
```

Fit statistic : Chi-Squared 57919.79 using 151 bins.

Test statistic : Chi-Squared 57919.79 using 151 bins.

Null hypothesis probability of 0.00e+00 with 145 degrees of freedom

Current data and model not fit yet.

- Select the spectral energy range of 2.8 to 12 keV for fitting.

```
XSPEC12>ignore **-2.8 12.0-**
```

```
58 channels (1-58) ignored in spectrum # 1
```

```
131 channels (210-340) ignored in spectrum # 1
```

- Perform fitting to minimize the fit statistic ( $\chi^2$ ). Obtain corresponding best-fit model parameters and their error estimates.

XSPEC12>fit

```
Model chisoth<1> Source No.: 1   Active/On
Model Model Component  Parameter  Unit      Value
par  comp
1    1    chisoth      logT       K         7.23437    +/- 3.17094E-03
2    1    chisoth      He         10.9000    frozen
3    1    chisoth      Li         1.64000    frozen
4    1    chisoth      Be         1.94000    frozen
5    1    chisoth      B          3.09000    frozen
6    1    chisoth      C          8.59000    frozen
7    1    chisoth      N          8.00000    frozen
8    1    chisoth      O          8.89000    frozen
9    1    chisoth      F          4.56000    frozen
10   1    chisoth      Ne         8.08000    frozen
11   1    chisoth      Na         6.93000    frozen
12   1    chisoth      Mg         8.15000    frozen
13   1    chisoth      Al         7.04000    frozen
14   1    chisoth      Si         8.10000    frozen
15   1    chisoth      P          5.45000    frozen
16   1    chisoth      S          7.27000    frozen
17   1    chisoth      Cl         5.50000    frozen
18   1    chisoth      Ar         6.38420    +/- 4.01372E-02
19   1    chisoth      K          5.67000    frozen
20   1    chisoth      Ca         6.72087    +/- 2.24401E-02
21   1    chisoth      Sc         3.71000    frozen
22   1    chisoth      Ti         5.56000    frozen
23   1    chisoth      V          4.54000    frozen
24   1    chisoth      Cr         6.21000    frozen
25   1    chisoth      Mn         5.93000    frozen
26   1    chisoth      Fe         7.90129    +/- 1.80268E-02
27   1    chisoth      Co         5.46000    frozen
28   1    chisoth      Ni         7.59931    +/- 7.74566E-02
29   1    chisoth      Cu         4.75000    frozen
30   1    chisoth      Zn         5.14000    frozen
31   1    chisoth      norm       1401.19    +/- 16.1127
```

-----

Fit statistic : Chi-Squared 472.19 using 151 bins.

Test statistic : Chi-Squared 472.19 using 151 bins.  
Null hypothesis probability of 2.74e-36 with 145 degrees of freedom



- Evaluate goodness-of-fit by calculating reduced  $\chi^2$  and plot fitted model with residuals (Figure 3).




Figure 3: CHIANTI isothermal plasma model fit to observed SoLEXS spectrum.

## 4.5 Notes on SoLEXS Spectral Analysis

This section provides important notes and clarifications regarding the characteristics of SoLEXS data and its use in spectral analysis.

### 4.5.1 Channel Binning in SoLEXS

The SoLEXS detector uses a Digital Pulse Processing (DPP) system to digitize photon energies into Pulse Height Analysis (PHA) channels. While the 9-bit digitization allows for 512 potential channels, to save on the data rate, DPP uses following design:

- Channels 1 to 168 are recorded individually, maintaining full energy channel bin width.
- Beyond the 168th channel, channels are grouped into pairs, effectively doubling the energy channel bin width.
- As a result, the total number of channels is reduced to 340 (Figure 4).




Figure 4: Energy binning in the spectral data

The instrument response stored in the RMF file is also grouped into pairs beyond the 168th channel. This maintains consistency between the spectral data and the response matrix.

#### 4.5.2 Response Calibration Below 2.8 keV

Although the lower energy limit for SoLEXS is 2 keV, the current calibration database files (ARF and RMF) are not optimized for energies below 2.8 keV. The response in the energy range 2 to 2.8 keV may not be accurate, and users are advised to exclude channels corresponding to these energies during spectral analysis. When fitting the spectrum, set the lower energy limit to 2.8 keV or higher to ensure reliable results.

#### 4.5.3 Detector Selection for Spectral Analysis

During the peak phase of the solar maximum in 2024, the SDD1 detector frequently experienced saturation due to high photon flux levels. As a result, data from SDD1 may not be available for spectral analysis during this period. We recommend using data from the SDD2 detector for spectral analysis, as it remained operational without saturation.

---

#### 4.5.4 Errors on Spectral Data

There are two sources of uncertainty in the spectral data:

- **Statistical Uncertainty:** This stems from the photon counting process and is assumed to follow Poissonian statistics.
- **Systematic Uncertainty:** This stems from uncertainties in the calibration of the instrument.

Currently, the systematic uncertainty in each energy bin is under analysis and is set to zero in the Type-I PI file. Users are advised to apply a model systematic error of 4% during spectral fitting to account for these uncertainties.

#### 4.5.5 Resolution Degradation at High Count Rates

The resolution of the SDDs is observed to degrade at high count rates, typically above  $10^5$  counts per second. Users should exercise caution when fitting spectral data recorded at such high count rates, as the degraded resolution may impact the accuracy of the fit. For reference, such high count rates are typically observed during high X-class flares for SDD2 and M-class flares for SDD1.